

List View Control Attributes Subwindow

► Accessible Using

1. Click on the "Attributes..." button in the list view control attributes window.

Entries

Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attributes Window	Represents
Font	Output field where the font currently selected is displayed.
...	Dialog box for selecting fonts.
DIL text	DIL-TEXT attribute value.
...	Dialog box for determining sources of DIL-TEXT attribute values.
Accelerator	Accelerator attribute value.
...	Dialog box for determining sources of Accelerator attribute values.
Context Menu	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
Wallpaper	WALLPAPER attribute value. Specifies the wallpaper (if any) displayed within the control.
Image List	IMAGE-LIST attribute value. Specifies the image list (if any) used to provide the images used by the control's items.
Background:	
Selection box	BACKGROUND-COLOUR-NAME attribute value.
...	Invokes dialog box for editing BACKGROUND-COLOUR-VALUE attribute value.
Foreground:	
Selection box	FOREGROUND-COLOUR-NAME attribute value.
...	Invokes dialog box for editing FOREGROUND-COLOUR-VALUE attribute value.
Help ID	HELP-ID attribute value. You must use the help topic's .h file to map the numerical ID that you enter here to the corresponding help topic ID (created by a markup in the .hlp file).
View Mode	VIEW-MODE attribute value. Specifies the control's display mode.
Drag Mode	DRAG-MODE attribute value. Indicates whether the control can act as the source in a drag-drop operation and, if so, which types of drag-drop operation it supports.

Entry in Attributes Window	Represents
Drop Mode	DROP-MODE attribute value. Indicates whether the control can act as the target in a drag-drop operation and, if so, which types of drag-drop operation it supports.
Spacing:	
X	SPACING-X attribute value. Specifies the width of the logical (in pixels) grid used in the icon view modes.
Y	SPACING-Y attribute value. Specifies the height of the logical (in pixels) grid used in the icon view modes.
W	SPACING attribute value. Specifies the width of the columns in list view mode.
Style:	
3-D border	STYLE attribute value. Control has sunken appearance. Note: The control does not have a sunken appearance if Windows XP styles are active.
Align vertically	STYLE attribute value. Items are arranged vertically in icon view modes.
Auto-arrange	STYLE attribute value. Items are maintained arranged on logical grid.
Snap to grid	STYLE attribute value. (Re-)positioned items are snapped to their nearest logical grid position.
No scroll	STYLE attribute value. Scroll bars not displayed in icon view modes.
No header	STYLE attribute value. Column header not displayed in report view mode.
No sort header	STYLE attribute value. Column headers are not click-sensitive.
Check boxes	STYLE attribute value. Displays check boxes next to the items.
Full row select	STYLE attribute value. Selection emphasis extends across full row in report view mode.
Grid lines	STYLE attribute value. Show grid lines in report view mode.
Header drag	STYLE attribute value. Allows re-ordering of columns by dragging their headers.
Label tip	STYLE attribute value. Show tooltip with label text when mouse cursor hovers over partially hidden labels.
Wrap icon labels	STYLE attribute value. Allows item labels to wrap across multiple lines.
Underline hot	STYLE attribute value. Underlines item under mouse cursor and enables single click item activation.
Underline cold	STYLE attribute value. Underlines all items and enables single click item activation.
No hide selection	STYLE attribute value. Keeps selection visible even when control no longer has the focus.
Border select	STYLE attribute value. Emphasizes the large icons of selected items via use of thick border.

Entry in Attributes Window	Represents
Hot-track select	STYLE attribute value. Automatically selects an item when the mouse cursor hovers over it for a short time..
Marquee select	STYLE attribute value. Allows selection of multiple controls in multiple-selection list view controls via "rubber banding" (drag rectangle).
Size to parent	STYLE attribute value. Control size automatically maintained to fill the client area of its parent.
<u>State:</u>	
Visible	VISIBLE attribute value. Control will be shown.
Enabled	ENABLED attribute value. Control can accept user input.
Modifiable	MODIFIABLE attribute value. Item labels may be edited.
Multiple selection	MULTI-SELECTION attribute value. Multiple items may be selected.
Sorted	SORTED attribute value. Items are initially sorted in alphabetic sequence.
Descending	DESCENDING attribute value. Items are initially sorted in descending alphabetic sequence.
Tooltips	HAS-TOOLTIP attribute value. If not set, display of the tool tip text (if any) for the items will be suppressed.
<u>Rectangle:</u>	The following four attributes decide the input field control's x and y axis position, its height and its width on the screen. X - RECTANGLE-X attribute value. Y - RECTANGLE-Y attribute value. W - RECTANGLE-W attribute value. H - RECTANGLE-H attribute value.
OK	Save settings and exit the window.
Cancel	Exit the window without saving the settings.
Help	Provides online help on the attributes window.

[Back to Attributes Windows for Dialogs and Dialog Elements.](#)